




Design by Karla Mokořová - Jewelry from BEADS


PRECIOSA Twin™

321 96 001; 2,5 x 5 mm



PRECIOSA Cut Rocailles

361 11 001; 15/0



PRECIOSA Rocailles

331 19 001; 6/0; 10/0




Preciosa Ornela introduces beads and seed beads from the PRECIOSA Traditional Czech Beads™ brand.

Preciosa-Ornela.com



NECKLACE SEWN USING PRECIOSA TERRA INTENSIVE COLORS

Chantelle



PRECIOSA

Chantelle

The PRECIOSA Traditional Czech Beads™ range now has an extended color base. We present the new pallet of 11 PRECIOSA Terra Intensive colors. We offer this pallet of intensive colors on 3 selected bead shapes, specifically on PRECIOSA Rocailles in the 3 sizes of 10/0, 8/0 and 6/0 and also on PRECIOSA Farfalle™ and PRECIOSA Twin™ seed beads. We have prepared a tutorial for the Chantelle sewn summer necklace as an example of their use.

Materials and tools:

PRECIOSA Bead Spacers (S)
111 69 036; 6 mm; 00030/26536; 16x



16A26 pink; 12x



PRECIOSA Imitation Pearls (IM)
131 19 001; 6 mm; 02010/70053; 15x



PRECIOSA Rocailles (R10)
331 19 001; 10/0
16A98 red; 36x



PRECIOSA Cut Rocailles (CH)
361 11 001; 15/0; 18503
(72x = 1; 1080x = 15)



16A91 orange; 72x



PRECIOSA Twin™ (T)
321 96 001; 2,5 x 5 mm;
16A98 red; 12x



16A86 yellow; 72x



16A91 orange; 24x



16A54 light green; 72x



16A86 yellow; 24x



16A58 dark green; 72x



16A54 light green; 24x



a hard 0.8 mm OSTEOFIX wire – 43 cm
(or memory wire); a carabiner; a no. 12 thin
needle; scissors; thread for the stringing -
S-lon (Fireline, DURAThread, Nymo);
a double counter-ring; 5 mm rings - 3x



16A58 dark green; 24x



16A38 blue; 24x



16A28 purple; 72x



16A28 purple; 24x



16A26 pink; 24x



PRECIOSA Rocailles (R6)
331 19 001; 6/0
16A98 red; 6x



16A91 orange; 12x



16A86 yellow; 12x



16A54 light green; 12x



16A58 dark green; 12x



16A38 blue; 12x



16A28 purple; 12x



snipping pliers, flat-nosed pliers, needle-nosed pliers





Difficulty: ●●●●●

Procedure:

Step 1:

Cut off about 1,3 m of thread.
Alternately string 6x R10 and 6x T
approximately 70 cm from the end.
Sew them into a circle so that the needle
emerges from the T. Sew through
the top hole of the same T. Don't cut
off the longer end of the thread. You will
use it to complete sewing the opening after
inserting the IM - see Step 10.





Step 2:

Gradually sew in 6x R6 between the T.
Tighten the seed beads. Sew through
them one more time in a circle as this will
strengthen the work.

Step 5:

String 1x R10 and sew through
the following R10. Continue the procedure
until the end of the row.



Step 3:

Gradually sew in 6x T between the R6.
Tighten the seed beads. Sew through them
one more time in a circle so that the needle
emerges from a T.

Step 6:

Once the last R10 has been strung, sew
through 2x R10 (1x R10 from the previous
row and 1x R10 from the existing row).
Sew through the last added R10 in a circle
one more time.




Step 4:

Sew through the top hole of the same T
and gradually sew in 6x R10 between
the T. Tighten the seed beads and sew
through them one more time in a circle so
that the needle emerges from an R10.

Step 7:

Sew through 1x R10 and 1x .




Step 8:
Gradually sew in 6x R10 between the T.



Step 12:
String 3x CH, 1x R10 and 3x CH.
Sew through 1x R10, 1x T and 1x R10.




Step 9:
Once the last R10 has been added, sew through the following T and 1x R10, which you added at the beginning of the existing row. Sew the thread in and cut it off.




Step 13:
String 3x CH, 1x R10 and 3x CH and sew through 1x R10.




Step 10:
Insert 1x IM into the opening on the second side. Follow Steps 5 to 9 to complete sewing the top of the ball.



Step 14:
String 3x CH and sew through 1x R10.



Step 11:
The needle should emerge from an R10. String 3x CH, 1x R10 and 3x CH and sew through 1x R10.



Step 15:
String 3x CH. Sew through 1x R10, 1x T and 1x R10.



Step 16:
Gradually complete the circumference of the ball according to steps 13-15 with the exception of the last insert. There, gradually sew in 3x CH between the R10. Sew in the thread and cut it off. Sew the remaining 14 balls in the same way.



Step 17:
Alternately string 16x S and 15x sewn balls onto a wire. The stringing begins and ends with an S. Create a loop on the ends of the wire. Insert the rings and the fastening into the loops.

